

QuickStart Guide--Audacity Personal for Pocket PC

1. Download the appropriate file AudacityDVRPPC_Personal.zip or AudacityDVRWM_Personal.zip from the Audacity website or the site of one of the Audacity vendors. The file can be saved to your desktop or simply opened.
2. Before installing the Audacity handheld application make sure you have the handheld installed and syncing with the PC.
3. Then double click the Audacity Personal Setup file. If this is a reinstall, the wizard will first ask if you wish to uninstall the existing application before installing the new application. You should say Yes. After the uninstall it will suggest a reboot. It is best to reboot although sometimes it is not necessary. If you have any type of problem, reboot.
4. The wizard will then proceed to install the new application. Just follow the wizard. It installs the desktop materials first including the conduit. Then the handheld applications are installed. CardSpeed is first, followed by AudAlarm, and finally Audacity Personal. AudAlarm is the Audacity Alarm handler and CardSpeed is a free utility to help judge the effectiveness of your SD Card. I suggest having your handheld plugged into the Sync cable during the install. You want to install all applications to Internal Memory.
5. At the end of the install, the wizard again asks you to reboot the PC.
6. Application files and the manual is installed under C:\Program Files\Audacity Personal DVR PPC\.
7. You will need to register the handheld application. In order for Audacity Audio to supply you a registration code we will need a hardware code from the Audacity handheld application. Launch Audacity on the handheld. Press the Settings icon (wrench in top toolbar), then Options and Registration. You will see a Registration ID. We need you to email that code to us (support@audacityaudio.com). The registration is generated from that code and returned to you. A full version of Audacity will run for 7 days without the code, but will then fail to run unless a valid code is entered on this same screen.
8. Get familiar with using the navigation pad to control your recordings. It gives you 5 controls with a single button. The Record button only gives you 1 control. Audacity gives you lots of button customization under the button setup. Audacity divides button control into 4 modes. A Record mode, a Play mode, an Idle mode (file open), and a Home mode (Idle, but no open file). A button function is provided for each button in each mode. For instance, in the idle mode navigation right is record, but in the record mode, it is pause / resume. Audacity provides easy intuitive one-handed recording.
9. Most users will want to record to the SD Card as it offers almost unlimited recording times. Select the SD Card from the Home Screen Menu. The default folder is Record. You may create additional folders or subfolders as you wish.
10. When syncing to the PC, the recorded files will Sync to the same folder structure you have on the handheld. The files can be found under C:\Audacity Personal DVR PPC\Recordings\.
11. We have covered the basics, but Audacity is full featured and offers many options and different settings. The manual covers detailed information.

Audacity Audio is available to provide complete installation and training for those lacking the time to wade through the manual. Our charge for this is \$ 30. We will set it up to satisfy your needs.

You will find Audacity very easy to use. Thanks for being an Audacity customer.

